

# Menus and Line Commands

The following topics describe all available menus, and the valid selections or line commands for each menu:

- Screens
  - Main Menu
  - Archived Tapes
  - Environment Maintenance
  - Working With Generated Jobs
  - Library Corrections
  - Display Jobs
  - Reports
  - Administration
- 

## Screens

Most System Maintenance Aid screens have one of the following two forms:

- Function menus present a selection list of possible functions. The user selects the function by entering the appropriate letter in the command line at the bottom of the screen.
- Object menus present a list of objects (e.g., available tapes, datasets on a tape). The user selects one of these objects **and** the function to be performed for this object by entering a "line command" next to the selected object. The list of possible line commands is displayed; the first two characters must be entered to issue the selected command.

# Main Menu

The Main Menu provides the following functions.

Example screen:

```

Enter a command, a direct command or press a PF-key.
11:56:38          *** SYSTEM MAINTENANCE AID ***          1999-06-09
User:  User_ID          - Main Menu -                      SMMENM11

          Command  Description
          - - - - -  - - - - -

          T          Tapes

          E          Environments

          Z          Library Corrections

          R          Reports

          A          Administration

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit                                  Canc

```

## Note:

Direct Commands are described separately (see Direct Commands for further information).

### T Tapes

After receiving a tape from Software AG, the customer should load the control data from the tape into SMA using a batch job. SMA then "knows" this tape and can display information on the tape and the products and datasets on it. The tape-handling functions also control the copying of datasets from tape to disk.

### E Environments

This is the central part of SMA: The customer describes the environments where Software AG products are installed or are to be installed. This description consists of the products to be installed, the various parameters (SVC number, dataset names, etc.) and possibly locally adapted JCL and generated JCL. The JCL generation for a specified environment is also started within this function.

### Z Library Corrections

ZAPs and other corrections which were delivered on an Software AG tape are also loaded into SMA and can be applied or removed using SMA functions. This has the advantage of improved control and documentation about where and when corrections have been applied. It is also possible to enter ZAPs manually into SMA and work with them subsequently.

### R Reports

Reports can be created to document the customer's environments, tapes and datasets, and the installation of Software AG products.

### A Administration

Administrative functions are available to specify a number of global parameters, unused tapes and/or products can be removed from the SMA data file.

## Archived Tapes

Tape and product dataset information, which has been loaded on the system, can be accessed using function T on the Main Menu.

Example screen:

```

Enter a command, a direct command or press a PF-key.
13:08:39          *** SYSTEM MAINTENANCE AID ***          1999-03-09
User:  User_ID          - Main Menu -                      SMMENM11

          Command  Description
+-----+-----+
!                                     !
!               Tapes               !
!                                     !
!  Select dataset access method:    !
!                                     !
!      _ Access datasets by Volser   !
!                                     !
!      _ Access datasets by Product !
!                                     !
+-----+-----+

Command ==> t
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit                      Canc

```

SMA prompts you to select how the information on datasets is to be accessed. Choices are made using either the volume serial number of the delivery tapes or by product code.

When "Access datasets by Volser" is selected, a list of tapes is displayed.

Example screen:

```

There is only 1 page available.
13:14:57          *** SYSTEM MAINTENANCE AID ***          1999-03-09
User:  User_ID          - Archived Tapes -          TPVOLM11

Reposition to Volser: _____
CMD  Volser  Op.Sys.  Description          Date Loaded
___  T16064  OS/MVS   SMA - QA - TAPE          1994-02-18

Command ==> _____

Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  --    ++          -    +      Print          Canc

```

The user may select a tape by marking it with one of the following line commands:

- **DA..Datasets**  
A list of all datasets on this tape is shown. The user may select one or several datasets by marking it/them with a line command. From this point, the user may control the copying of datasets from tape to disk.
- **JC..JCL-Generation**  
JCL is generated for copying those datasets from the selected tape to disk which have been marked as "to be copied". Note that this JCL will also be generated automatically when JCL generation for product installation is requested in the "Environment" part of SMA.
- **JO..Jobs**  
This command displays the "Generated Jobs" screen for jobs generated with the JC..JCL Generation function.
- **PR..Products**  
A list of all products on this tape is shown. The user may select one of the displayed products. As a result, the list of datasets for this product, that are contained on this tape will be displayed.
- **RE..Readme**  
The tape may contain texts explaining the status or the purpose of the tape. Command RE will display this text.
- **SE..Set-copied**  
The dataset status "to be copied" is reset for all datasets on the selected tape.

**Note:**

In the Command Area, PF1 can be used to obtain Help, PF2 returns you to Main Menu, PF3 is used to exit, PF4 returns you to the top of list, PF5 returns you to the bottom of list, PF7 can be used to scroll to the previous page, PF8 to scroll to the next page PF9 is used to print a listing, and PF12 is cancel.

If PR (Products) was entered as a line command, press Enter, and the "Products On Tape" screen appears.

Example screen:

```

Please mark one product.
13:06:58          *** SYSTEM MAINTENANCE AID ***          1999-03-11
User:  User_ID          - Products On Tape -          TPVPRM11

Reposition to Product: _____ Volser: T16064

  M   Product      Description
  _   ACI525      ADABAS CICS INTERFACE
  _   ADA525      ADABAS
  _   AII525      ADABAS IMS/DC INTERFACE
  _   AOS225      ADABAS ONLINE SERVICES
  _   EDT152      NATURAL EDITOR
  _   ESX132      ENTIRE SYSTEM SERVER INTERFACE
  _   NAF225      NATURAL ADVANCED FACILITIES
  _   NAT225      NATURAL
  _   NA2508
  _   NA2510
  _   NA2511
  _   NCI225      NATURAL CICS INTERFACE
  _   NDB231      NATURAL FOR DB2
  _   NDL225      NATURAL FOR DL/1

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++          -    +      Print      Canc

```

Mark the desired item to display datasets for a specific product.

If DA (Datasets) was entered as a line command for "Datasets on Tape", press Enter, and the "Product Datasets" screen appears.

This screen is explained later in section Product Datasets.

## Access Datasets by Product

When "Access Datasets by Product" was selected from the "Archived Tapes" entry window, the following screen is displayed.

Example screen:

```

Enter a command, a direct command or press a PF-key.
13:17:11          *** SYSTEM MAINTENANCE AID ***          1999-03-09
User:  User_ID          - Main Menu -                      SMMENM11

      Command  Description
      +-----+
      !                                     !
+-----+
!                                     !
! Operating system .....: OS/MVS__      !
! Library group (optional) ...: _____ !
!                                     !
+-----+
      !      _ Access datasets by Product      !
      !                                     !
      +-----+

Command ==> t
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit                                  Canc
  
```

Enter the Operating system, if not already displayed, and the Library group, if desired.

Use the Library group option only when selecting products where datasets/copies exist for a specific library group.

Press Enter, and the "Datasets by Product" screen appears, and a list of products for the selected tape is displayed.

Example screen:

```

Please mark with 'x'.
13:43:23          *** SYSTEM MAINTENANCE AID ***          1999-03-09
User:  User_ID    - Tapes: Datasets by Product -          TPPERDM11

Reposition to Product: _____ Op/Sys: OS/MVS   Lib-Group:
      M      Product      Description
      -      ACI525      ADABAS CICS INTERFACE
      -      ADA525      ADABAS
      -      AII525      ADABAS IMS/DC INTERFACE
      -      AOS225      ADABAS ONLINE SERVICES
      -      EDT152      NATURAL EDITOR
      -      ESX132      ENTIRE SYSTEM SERVER INTERFACE
      -      NAF225      NATURAL ADVANCED FACILITIES
      -      NAT225      NATURAL
      -      NA2508
      -      NA2510
      -      NA2511
      -      NCI225      NATURAL CICS INTERFACE
      -      NDB231      NATURAL FOR DB2
      -      NDL225      NATURAL FOR DL/1

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++          -  +          Print          Canc

```

This is a list of those products for which datasets are on the selected tape. The user may select the datasets of a product for processing by marking it with an "X".

If a product is contained on multiple tapes, the following screen appears.

Example screen:

```

There is only 1 page available.
11:08:25          *** SYSTEM MAINTENANCE AID ***          1999-04-12
User:  User_ID      - Tapes:  Volsers with Product -      TPPERDM21

Reposition to Volser: _____ Op/Sys: OS/MVS   Lib-Group:
M  Volser  Description                               Creation
-  T10857  test                                       1993-03-19
-  T10958  NAT225 and Co-products                     1993-05-27

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11--PF12---
      Help  Menu  Exit  --    ++          -    +      Print          Canc

```

Mark desired item with "X" to display datasets.



## Product Datasets

When a product was marked on the "Datasets by Product" screen or when a product was selected on the "Volsers with Product" screen, the list of datasets on the selected tape is displayed.

Example screen:

```

There is only 1 page available.
13:52:11          *** SYSTEM MAINTENANCE AID ***          1999-03-09
User:  User_ID          - Product Datasets -          TPPDSM11

Reposition to Dataset: _____          Volser: T16064
Cmd  Dataset Name      Description          On Disc As          C
___  NAT225.ERRN        Error messages file
___  NAT225.EXPL        Example INPL file
___  NAT225.INPL        INPL dataset
___  NAT225.JOBS        MVS Example jobs for installat
___  *      COPY IN     GROUP: TSTLIB          TSTLIB.NAT225.JOBS    Y
___  NAT225.LOAD        MVS Load dataset          SAGLIB.NAT225.LOAD    Y
___  *      COPY IN     GROUP: TSTLIB          TSTLIB.NAT225.LOAD    Y
___  NAT225.SRCE        MVS Source dataset
___  *      COPY IN     GROUP: TSTLIB          TSTLIB.NAT225.SRCE    Y
___  NAT225.SYSF        System file

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  --  ++          -  +      Print          Canc

```

Select one or several datasets for processing by marking it or them with one of the following commands:

- **DE.. Delete-Copy**  
This command deletes the table entry describing the copy of a dataset (library). The record pointing to the Software AG delivery group cannot be deleted.  
**Note:**  
This command does not delete the dataset itself; only SMA's table entry for this dataset is deleted.
- **MA.. Mark-For-Copy**  
The dataset is marked as "to be copied". During the next JCL generating step, the JCL required for copying from tape to disk will be generated for all datasets on all tapes which have been marked.
- **MO.. Modify**  
A description of the selected dataset is shown. Some of the fields of this dataset description can be changed by the user.
- **RE.. Reset-Mark**  
This command resets the status of a dataset from "marked to be copied" to "not marked".

## Dataset Parameters

When a dataset is selected via the command MO (Modify) from the "Product Datasets" screen, the dataset parameters are displayed.

Example screen:

```

Modify dataset parameters.
12:09:48          *** SYSTEM MAINTENANCE AID ***          1999-03-10
User:  User_ID          - Copy Parameters -          TPCDSM11

Volser ..... T16064
Name on tape  NAT225.I008

Description ..... 008.INPL correction
Symbolic Dataset Name NAT225.I008
Dataset Organization PS
Size (Kilo byte) .... 40
Marked For Copy .....
Dataset created on .. 93-11-04      16:01:05
Dataset copied on....

Library Grp  SAGLIB_____
Name on Disk _____
Disk ..... _____
Device Type  _____

Command ===>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit                                  Canc

```

The following dataset parameters which are used when copying datasets from tape to disk may be changed:

- Library Group
- Name on Disk
- Disk where the dataset is stored
- Device Type of this disk

If the dataset has been marked "to be copied", SMA fills the above fields with default values if they are blank. See Step 2: Copying Datasets from Tape to Disk in section Using System Maintenance Aid for the definition of the default values.

Note that SMA uses "Name on Disk" to determine whether the dataset resides on disk. A blank name indicates that the dataset is currently not available on disk.

## Environment Maintenance

When function E is chosen in the Main Menu, the list of all environments is displayed.

Example screen:

```

There is only 1 page available.
12:36:23          *** SYSTEM MAINTENANCE AID ***          1999-03-10
User:  User_ID          - Environment Maintenance -          ENMENM11

Reposition to Environment: _____
Cmd  Environment  Op.Sys.  Description
___  BS2000       BS2000  DEFAULT-ENVIRONMENT FOR BS2000
___  BS2TST       BS2000  DEMO FOR BS2000
___  OS/MVS       OS/MVS   DEFAULT-ENVIRONMENT FOR OS/MVS
___  TEST        OS/MVS   DEMO AND INTRODUCTION
___  UPROD       OS/MVS   USER PRODUCTION
___  APPL        OS/MVS   APPLICATION DEVELOPMENT

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++      -  +      Print      Canc

```

The user may select an environment by marking it with one of the following line commands:

- **CH..Check Environment**  
This command executes a number of checks to find out incorrect specifications, for example, when a subproduct of Natural (e.g., Con-nect) is marked for installation, but Natural itself is neither installed nor "to be installed". Although many checks are performed, it is not possible to detect every inconsistency of parameter values.
- **CJ..Copy Environment Jobs**  
This command copies all the jobs which exist in this environment. You can specify a new name for the job group and assign a common prefix for the job names.
- **CO..Copy Environment**  
This command creates a new environment by copying an existing one. The user is prompted for a short descriptive text for the environment. The first line of this description will be used in the display-list of all environments.  
The following parts of the environment are copied:
  - old and new values of all parameters
  - JCL skeletons, if the existing environment is not a default environment
  - list of all available products, with the status of the products set to "not installed".
- **DE..Delete Environment**  
This function deletes the environment from SMA's control file after the user has been prompted to confirm the request. Only SMA internal data is deleted, nothing happens "outside" of SMA, i.e., there is no "de-install" feature in SMA.  
A default environment cannot be deleted.
- **JC..JCL-Generation**  
This command starts the JCL generator. See section JCL Generation below for a description of this process. If an error is detected, it can be corrected with the MODIFY command.

- **JO..Jobs**  
This command displays the "Generated Jobs" screen for the current environment.
- **MO..Modify Environment**  
This line command displays the screens in which the user can describe the customer's installation of Software AG products (see section Modifying an Environment below).
- **SA..Saved Environment Jobs**  
Invokes the Saved Jobs for Environment menu to process the saved jobs whose group name is an environment name.
- **SE..Set Installed**  
This command resets status information:
  - All products which have the status "to be installed" are marked as "installed".
  - Old parameter values are replaced by new values if specified.
  - The status of linked modules which have been changed by SMA's "Library Correction" function is reset from "to be relinked" to "ok".

This function is useful in two situations:

  - After describing an existing environment, the user calls this function to document that the products in this environment are already installed.
  - The last job generated during JCL generation executes this function in batch. Instead of using this job, the user may execute this function in dialog after successful execution of all generated jobs (except this last one).
- **TE..Text Description**  
The descriptive text for this environment can be modified. When this function is selected from the "Modify Environment" screen, a window appears providing four input lines. On these four lines, the purpose of each environment can be described in a short text. These lines appear in the reports about environments and help the user keeping track of input into SMA. The first of these four lines of text will also be displayed in the "Environment Maintenance" screen.
- **CL..Clone Environment**  
This command duplicates an environment. It creates a new environment by copying an existing one. The user is prompted for a short descriptive text for the environment. The first line of this description will be used in the display-list of all environments.  
The following parts of the environment are copied:
  - old and new values of all parameters
  - JCL skeletons, if the existing environment is not a default environment
  - list of all available products, with the same status.
- **RN..Rename Environment**  
This command renames an environment.

## JCL Generation

The JCL generator is activated using the line command JC (JCL Generation) from the "Environment Maintenance" screen. JCL generation in dialog mode consists of the following steps:

1. The JCL generator first evaluates which parameter values are new and what products are "to be installed", and produces a list of all installation steps required for these changes. In this step, a lot of control data must be evaluated, thus it can take some time for its completion.
2. The "Installation Guide" indicating the generated jobs and steps is displayed. This list can be printed by pressing PF9. The printout will be useful as a checklist during the process of submitting and executing the generated jobs later on.  
By pressing Enter, the next page of this report can be displayed. PF6 can be used to skip the display and go on with JCL generation.
3. JCL generation itself starts. The job and step number currently generated is displayed at the bottom of the screen.

**Note:**

If Enter or a PF key is pressed during this process, an error may occur, and JCL generation will be interrupted.

After JCL generation has been completed, the number of errors detected during the generation is displayed. If this number is not equal to 0, the user should check whether a user modification of a JCL skeleton caused an error. If not, Software AG support personnel must be contacted.

## Modifying an Environment

When the line command MO (MODIFY) is entered from the "Environment Maintenance" screen, the data describing the installation is displayed.

Environment Maintenance screen:

---

This menu offers the following options:

- **Modify parameters accessed by name**  
The list of all parameters in alphabetical order will be displayed for this environment by name, for displaying and modifying their values.
- **Modify active parameters accessed by name**  
This function is identical with the function "Modify Parameters accessed by name" except that only the *active* parameters are accessed.  
Active parameters are those parameters which were referenced during a JCL generation. This internal flag was introduced with SMA version 1.3.1, therefore, before the first JCL generation was executed with SMA version 1.3.1., all existing parameters are considered "inactive".
- **Modify parameters accessed by group**  
The parameters are combined in groups. If the user selects one of these groups on the "Parameter Group" screen (see below), the parameters of this group are shown, and new values may be entered.
- **Modify active parameters accessed by group**  
This function is identical with the function "Modify Parameters accessed by group" except that only the *active* parameters are accessed.
- **Install Products**  
The list of products will be displayed for selection of the products to be installed in this environment.
- **Install Corrective IUPD (INPLs,ERRNs)**  
A list of those corrections, which can be installed into a Natural system file, is displayed for selection. Typically, these are INPL problem tapes.
- **Modify JCL Skeletons**  
When this function is selected, the list of JCL skeletons available is displayed.

## Modify Parameters / Active Parameters Accessed by Name

When this function is selected from the "Environment Maintenance" screen, the list of parameters appears, indicating the parameter name and value.

The parameters have two values: the installed value and the new value. The new value will be taken during the next JCL generation, and it will replace the installed value with the next SET-INSTALLED command.

A new value may be entered in the corresponding column, or one of the line commands used with the function "Modify Parameters accessed by Name", which are restricted to the selected group.

Example screen:

```

Enter new value(s) or line command(s)
12:55:48          *** SYSTEM MAINTENANCE AID ***          1999-03-10
User:  User_ID    - Modify Parameter Values -              ENPRMM11

Reposition to Parameter: _____ Env.: TEST
Cmd  Name of Parameter    Installed Value    New Value
___  ACF2                  _____
___  ADA-CREATE-NEW-DB     Y                  _____
___  ADA-INSTAL-RAI       N                  _____
___  ADA-RAI-MINGENS      5                  _____
___  ADACICS              ADABAS              _____
___  ASIZE                32                  _____
___  ASM-DDRESULT         SYSLIN              _____
___  ASMBLR               IEV90              _____
___  ASYNC                _____
___  BPID                 0                  _____
___  BTSO-BATCH           NDBBTSO            _____
___  CDYNAM              10                  _____
___  CICS3                _____
___  CICS3-3              _____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --    ++          -    +    Print          Canc

```

The user may enter a new value in the corresponding column or enter one of the line commands described below.

- **DI.. Display**  
A description of the selected parameter is displayed. (Understanding the complete set of parameters is more easily accomplished by report "P" available in SMA's "Reports" branch.) If this command is used, a screen appears.
- **LO.. Long Value**  
If the new value for a parameter does not fit into the corresponding column, the command LONG must be used. A window is displayed, allowing for the input of values with up to 72 characters. If this command is used, a window appears.
- **SD..Set Default**  
Sets the actual value to the value specified in the default environment.
- **SE..Set Blank**  
This command is used to set the new value of a parameter to blank. (This must be done with this command to tell the JCL generator that this blank really is the new value.)
- **SI..Set Inactive**  
Resets the internal active flag to inactive.
- **TV..Transfer Value**  
This command is only valid in the default environment. It transfers the values specified in the default environment to all other environments.

The parameters have two values: the installed value and the new value. The new value will be taken during the next JCL generation, and it will replace the installed value with the next SET-INSTALLED command.



## Modify Parameters / Active Parameters Accessed by Group

When this function is selected from the Environment Maintenance screen, the list of parameter groups appears.

Parameter Groups screen:

```

12:56:33          *** SYSTEM MAINTENANCE AID ***          1999-03-10
User:  User_ID          - Parameter Groups -          ENPRMM21

Reposition to Group: _____          Environment: OS/MVS

          M          Group
          -          ADABAS
          -          BASIC
          -          DCPROD
          -          FILNUM
          -          LIBGRP
          -          NAF
          -          NAT
          -          NATPRM
          -          NCI
          -          NCO
          -          NDB
          -          NDL
          -          NII
          -          NTI

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++          -  +          Print          Canc

```

Mark one of the existing Groups. A screen similar to that previously described for "Modify Parameters / Active Parameters Accessed by Name" appears.

## Install Products

When "Install Products" is selected from the "Environment Maintenance" screen, the list of all products is displayed.

Example screen:

```

Enter a command, a direct command or press a PF-key.
16:12:17          *** SYSTEM MAINTENANCE AID ***          1999-06-07
User:  User_ID          - Product List -          ENPRDM11

Reposition to Product: _____ Environment: TEST
Cmd  Product  Description  Status
___  NCI233   NATURAL CICS INTERFACE  installed
___  NCI234   NATURAL CICS INTERFACE  to be installed
___  NCI312   NATURAL CICS INTERFACE  -
___  NCL211   NATURAL CONSOLE MANAGEMENT  -
___  NCL212   ENTIRE EVENT MANAGEMENT  -
___  NCO233   NATURAL COMPLETE INTERFACE  -
___  NCO234   NATURAL COMPLETE INTERFACE  -
___  NCO311   NATURAL COMPLETE INTERFACE  -
___  NCO312   NATURAL COMPLETE INTERFACE  -
___  NDB233   NATURAL DB2 INTERFACE  -
___  NDB234   NATURAL FOR DB2  -
___  NDB312   NATURAL FOR DB2  -
___  NDL233   NATURAL DL/1 INTERFACE  -
___  NDL234   NATURAL DL/1 INTERFACE  -

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++          -  +      Print          Canc

```

In this screen, all products are listed which are known in this SMA file. This list of products is the same for all environments, but the status of each product may differ between environments.

The user may select one or several products by marking it or them with one of the following commands:

- **IN.. Install**  
The product receives the status "to be installed". The products having this status will actually be processed by the next JCL generation for this environment.
- **RE.. Reset Status**  
This command removes the status "to be installed". It is used to reset this status if the INSTALL command has been issued inadvertently.
- **UN.. Un-install**  
The status "installed" is set to "-", meaning "not installed". Note that in the present version of SMA no JCL to "un-install" a product is generated. This command only causes the status to be changed in SMA internal tables and has no effect "outside" of SMA.
- **RM..Show Readme**  
Displays the Readme file of the product. This file contains information about the installation of these products using SMA.

## Install Corrective IUPD - INPLs and ERRNs

When "Install Corrections in System files (INPLs, ....)" is selected from the "Environment Maintenance" screen, the list of all corrections for Natural system files is displayed.

Example screen:

```

Enter a command, a direct command or press a PF-key.
14:49:18          *** SYSTEM MAINTENANCE AID ***          1999-06-13
User:  User_ID          - Correction List -          ENPRDM11

Reposition to Correction : _____ Environment: TEST
Cmd  Correct.  Description          Status
___  P06027    PROBLEM SOLUTION INPL    to be installed
___  P07668    PROBLEM SOLUTION INPL FOR SMA111    -
___  P09489    ADABAS TEXT RETRIEVAL 1.3.3    -
___  P16005    PROBLEM SOLUTION INPL    -
___  P19509    PROBLEM SOLUTION FOR P119509    -
___  P19756    PROBLEM SOLUTION FOR P119756    -
___  P22126    PROBLEM SOLUTION FOR P122126    -
___  P24378    PRD322 SOLUTION TO PROBLEM: 124378    -
___  P24805    SAT211 SOLUTION TO PROBLEM: 124805    -
___  P97531    (=NE2531)NSC225 CORRECTIVE TAPE-31    -
___  P97602    (=NE2602)NSC226 CORRECTIVE TAPE-02    -
___  P97603    (=NE2603)NSC226 CORRECTIVE TAPE-03    -
___  P97605    (=NE2605)NSC226 CORRECTIVE TAPE-05    -
___  P97612    (=NE2612)NSC226 CORRECTIVE TAPE-12    -

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++          -  +          Print          Canc

```

In this screen, all corrections are listed which are known in this SMA file. This list of corrections is the same for all environments, but the status of each may differ between environments.

The user may select one or several corrections by marking it/them with one of the following commands:

- **IN.. Install**  
The correction receives the status "to be installed". The corrections having this status will be processed by the next JCL generation for this environment.
- **RE.. Reset Status**  
This command removes the status "to be installed". It is used to reset this status if the INSTALL command has been issued inadvertently.
- **UN.. Un-install**  
The status "installed" is set to "-", meaning "not installed". Note that in the present version of SMA no JCL to "un-install" a correction is generated. This command only causes the status to be changed in SMA internal tables and has no effect "outside" of SMA.

## Modify JCL Skeletons

After selection of this function from the "Modify Environment" screen, a list of all skeletons available, including a short explanation for each skeleton, is displayed.

Example screen:

```

Enter a command, a direct command or press a PF-key.
12:52:36          *** SYSTEM MAINTENANCE AID ***          1999-03-10
User:  User_ID          - Modify JCL Skeletons -          ENSKLM11

Reposition to Skeleton: _____ Environment: OS/MVS
Cmd E  Skeleton Name      Version  Description
___    ACI-CMDLNK          93-03-09  COMMAND LEVEL LINK ROUTINE ASSEMBLY
___ x  ACIINSTR             93-03-29  INSTRUCTIONS FOR ADABAS CICS INTERFACE
___    ADA-FILES           93-03-29  INCLUDE: DD-CARDS FOR THE ADABAS-FILES
___    ADACPL              92-12-10  ADABAS COUPLE FILES (V5)
___    ADADEF5             92-12-10  ADABAS DEFINE DATABASE
___    ADAEXPL             92-12-10  ADABAS EXAMPLES WITHOUT FILES
___    ADAEXPL-F           92-12-10  ADABAS EXAMPLES WITH FILES
___    ADAFRM-RAI          93-04-01  ADABAS ALLOCATE AND FORMAT RAI-FILE
___    ADAFRM5             92-12-10  ADABAS ALLOCATE AND FORMAT DATABASE-FILE
___    ADALIBS             92-12-10  INCLUDE: DD-CARDS FOR ADABAS
___    ADALOD              93-08-09  ADABAS LOAD FILE (V5)
___    ADAMAT              92-12-10  INCLUDE: ADABAS MIGRATION AID TABLE
___    ADANUC5             92-12-10  ADABASE NUCLEUS JOB
___    ADARAI-INST         93-03-29  INSTRUCTIONS FOR ADABAS REFLECTIVE DATAB

Command ===>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  --  ++      -      +      Print      Canc

```

### Note:

The skeletons which have already been modified for this environment are marked with an "X" in column "E".

The JCL skeletons are used during JCL generation to expand the installation steps into executable JCL. These JCL skeletons are supplied by Software AG, but they may be modified by the user. Modifications of JCL skeletons in the default environment are valid for all other environments, whereas modifications of JCL in a user environment are valid for this environment only.

The following line commands may be selected and used:

- CO.. Copy Skeleton
- DE.. Delete User Skeleton
- DI.. Display Skeleton
- MO.. Modify Skeleton
- PR.. Print Skeleton

## Modify Skeleton

When the line command MO (Modify Skeleton) is entered on the "Modify JCL Skeletons" screen, the Natural editor for modifying the JCL Skeleton appears.

Example screen:

```

Command ===>                                     > +
Top      Environment: TEST                        Skeleton: ADADEF5      ....7..
0010  /**
0020  /** ADABAS ADADEF UTILITY
0030  /**
0040  //DEF#S-SEQ# EXEC PGM=ADARUN
0050  //STEPLIB DD DSN=#D-DSN-D(ADA&&&.LOAD)#,DISP=SHR
0060  #I-ADA-FILES#
0070  //DDPRINT DD SYSOUT=#V-SYSOUT#
0080  //DDDRUCK DD SYSOUT=#V-SYSOUT#
0090  //MPMDUMP DD SYSOUT=#V-SYSOUT#
0100  //DDCARD DD *
0110  ADARUN DB=#V-DBID#,DE=#V-DB-DEVICE#,SVC=#V-SVC#,PROG=ADAEF
0120  //DDKARTE DD *
0130  ADADEF DEFINE
0140  ADADEF DBIDENT=#V-DBID#
0150  ADADEF DBNAME=#V-DBNAME#
0160  ADADEF MAXFILES=#V-DB-MAXFILS#
0170  ADADEF ASSODEV=#V-DB-DEVICE#
0180  ADADEF ASSODEV=#V-DEVICE-A2#
0190  ADADEF ASSODEV=#V-DEVICE-A3#
0200  ADADEF ASSODEV=#V-DEVICE-A4#
      ....+....1....+....2. Press PF11 to edit conditions No.of.Lines: 44

```

### Note:

Use the "," as the escape character for line commands. Use PF11 to shift the screen to the right to view line conditions. Use PF10 to shift back (toggle effect).

Refer to JCL Skeletons for a further explanation of skeleton modification.

## Working with Generated Jobs

If the function JO (Jobs) is entered in the "Environment Maintenance" screen after JCL generation has been performed, the list of all generated jobs is displayed.

Example screen:

```

There is only 1 page available.
11:13:50          *** SYSTEM MAINTENANCE AID ***          1999-04-12
User:  User_ID          - Generated Environment Jobs -          ENJOBM11

Reposition to Job: _____ Environment: TEST

  Cmd      Job      Description      Status
  ---      ---      ---      ---
  ---      Report    Installation Guide    Open
  ---      T614      COPY DATASETS FROM TAPE    Submitted
  ---      P060      READ ME; DO NOT SUBMIT    Open
  ---      I008      ALLOCATE DATASETS      Submitted
  ---      I009      COPY DATASETS      Submitted
  ---      I051      MIGRATION JOB      Submitted
  ---      I055      ASSEMBLIES OF BATCH NATURAL    Submitted
  ---      I060      PARM + LINK BATCH NATURAL    Submitted
  ---      I061      INPL NATURAL APPLICATIONS    Submitted
  ---      I070      PREPARATIONS ONLINE NATURAL    Submitted
  ---      I080      PARM + LINK ONLINE NATURAL    Submitted
  ---      I100      READ ME; DO NOT SUBMIT    Open
  ---      I200      SETUP - JOBS      Submitted
  ---      I999      SMA COMMIT AND ENV.REPORT    Open

Command ===>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++      -      +      Print      Canc

```

- **MO.. Modify Job**

The generated job is displayed. The user can browse through the generated job, using PF7 and PF8 to scroll backwards and forwards, print the job, or modify it before submitting it to the operating system for execution. Usage of the editor for modification is explained in Using the Editor and Help Facility.

**Note:**

SMA is designed to make changes in the generated jobs unnecessary. If frequent changes of the jobs are required, the job skeletons which are used during JCL generation should be changed. Refer to JCL Skeletons or the appropriate report to find out which skeletons are involved.

- **SU.. Submit Job**

The generated job is passed to the operating system for execution. The status and successful execution of a job are **not** checked by SMA; this must be done by the user. Within SMA, a job can have the status:

- OPEN: The job has been generated and has not yet been submitted.
- SUBMITTED: The job has been submitted. It is possible to submit a job, change it and re-submit it.

Note that the order of submitting the generated jobs is checked: A job may only be submitted if all jobs preceding this job in the list of jobs have already been submitted.

- **DE.. Delete Job**

With this command, a job can be deleted manually by the user. Normally, the stored generated jobs should be deleted by the user after successful execution of all jobs.

- **CO.. Copy Job**

Jobs of an environment must be deleted before the next JCL generation. A user who wishes to keep a job (as an example or for later usage) may enter the COPY command for this job. SMA asks for a new name and "job group". If the "Saved Jobs" function is entered from SMA's Administration Menu, the copied job can be found under the specified name.

- **PR.. Print Job**

The selected job will be printed.

## Library Corrections

In this section of SMA, you control how corrections ( i.e., ZAPs, Source Changes, and Module Replacement) are applied to the Software AG Product Libraries.

When function Z is chosen in the Main Menu, a list of all library groups is displayed.

Example screen:

```

Enter a command, a direct command or press a PF-key.
12:27:40          *** SYSTEM MAINTENANCE AID ***          1999-06-09
User:  User_ID      - Correction List of Library Groups -      COLBGM11

Reposition to Op.Syst: _____ Lib.Group: _____

      Cmd  Op. System  Library Group
      ---  ---
      ___  BS2000     $SAG
      ___  BS2000     SAGLIB
      ___  OS/MVS     TSTLIB
      ___  OS/MVS     SAGLIB

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++  AddZ  -  +  Print  Canc

```

The user may select a correction for a library group by marking it with one of the following line commands:

- **DI.. Display Corrections**  
All possible corrections for the selected library group are displayed. If this command is used, the screen "ZAPs and Source Changes" appears.
- **JC..JCL-Generation**  
This command performs JCL generation for corrections in the library group with the status "to be applied" or "to be undone". See JCL Generation in this section for a description of this process.
- **JO..Jobs**  
This command displays the "Generated Jobs" screen for this library group.
- **SE..Set-Applied**  
This command resets status information: All corrections within the library group with the status "to be applied" or "to be undone" receive the status "applied" or "undone" with this command.



## Display Corrections

If DI (Display Corrections) is entered as a line command in "Correction List of Library Groups" a screen listing all ZAPs and source changes for a library group appears:

13:31:17	*** SYSTEM MAINTENANCE AID ***	1999-07-08
User: TSL	- Zaps and Source Changes -	COZAPM11
Reposition to Change: _____		Library Group: SAGLIB
Cmd	Change No. Tp.	Dataset Name Ed. Status
___	AN52445 Z	SAGLIB.ADA522.LOAD Y
___	AN52455 Z	SAGLIB.ADA525.LOAD Y
___	AN52456 Z	SAGLIB.ADA522.LOAD Y
___	AN52457 Z	SAGLIB.ADA522.LOAD Y Applied
___	AN52461 Z	SAGLIB.ADA522.LOAD Y
___	AN52494 Z	SAGLIB.ADA522.LOAD Y
___	AN52516 Z	SAGLIB.ADA522.LOAD Y Applied
___	AN52537 Z	SAGLIB.ADA522.LOAD Y Applied
___	AN52683 Z	SAGLIB.ADA523.LOAD Y
___	AN52728 Z	SAGLIB.ADA524.LOAD Y
___	AN52729 Z	SAGLIB.ADA524.LOAD Y
___	AN52857 Z	SAGLIB.ADA524.LOAD Y
___	AN52954 Z	SAGLIB.ADA525.LOAD Y
___	AN52966 Z	SAGLIB.ADA525.LOAD Y To Be Applied
Enter a command, a direct command or press a PF-key.		
Command ==>		
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---		
Help Menu Exit -- ++ - + Print Canc		

### Note:

The field "Reposition to Change" at the top of the screen provides the possibility to start the list of changes at the specified change. You can use this repositioning to show the corrections for a specific product (due to the naming conventions of Software AG product corrections).

This list shows the dataset names of the affected libraries, and gives the following information per correction:

- number of the change, used for identification purposes
- its type (Z: ZAP, S: source change, L: load module replacement)
- status of the change

The status of a change may be any of the following:

- "to be applied" The line command APPLY has been entered for this correction, but the direct command SET-APPLIED has not yet been executed.
- "applied" The line command APPLY has been issued for this correction, and SET-APPLIED has been executed.
- "to be undone" The line command UNDO was entered for this correction, but the direct command SET-APPLIED was not executed.  
The generated job will contain the ZAP in a "reverse" form, where all VERIFY(s) are converted to REPLACE(s) and vice versa.
- "undone" The line command UNDO was entered for this correction, and SET-APPLIED was executed.
- blank The correction was neither applied nor undone.

The following line commands are possible:

- AP.. Apply Correction  
Sets the status for this change from blank or "undone" to "to be applied".
- CO.. Copy a Correction  
A window appears asking for target parameters for copying the correction.
- DE.. Delete Correction  
The change in the selected library group is deleted from SMA.
- DI.. Display Correction  
The selected change is displayed. If this command is used, a screen showing the text of the correction appears.
- MO.. Modify Correction  
This allows editing of the change. This command is only valid if there is a "Y" in the "Ed" column in the list of changes. If this command is used, the screen "Modify a Correction" appears.
- RE.. Reset Status  
This command sets the status from "to be applied" to blank or from "to be undone" to "applied".
- UN.. Undo Correction  
Sets the status from "applied" to "to be undone".

**Note:**

The line commands MODIFY and DELETE are only possible if the change is not applied in any library group.

## Modify Correction

If MO (Modify Correction) is entered as a line command the following screen appears:

```

Please edit. (Escape character for line commands is ",")
Command ==>
Top      Change: AN52494      Type: Z DSN: ADA522.LOAD      > +
.....6.....+.....7..
0010 *   ZAP NO:      AN52494
0020 *   PRODUCT:     ADA522
0030 *   MODULES:     ADANC2/ADANC9
0040 *   KEYWORDS:    ADANET
0050 *   PROBLEM:     A PET COMMAND (PRILIMINARY ET) IS ONLY PERMITTED
0060 *                  IN AN ADANET ENVIRONMENT, NOT PERMITTED ON A NUCLEUS
0070 *                  RUNNING WITH ADANET=ISO.
0080 *
0090 NAME ADANC2
0100 VER 0080 0002
0110 VER 009A 0000
0120 VER 1108 92D7,CEB6,9205,CEB4,95C5,C023,4770,904E
0130 VER 1118 D203,C060,C03C,D201,C078,C01A,5810,AC54
0140 VER 1128 0521,9680,E053
0150 REP 1108 95C9,A2C4,4770,9042,9240,C022,47F0,905C
0160 REP 1118 92D7,CEB6,9205,CEB4,D203,C060,C03C,5810
0170 REP 1128 AC54,05BB,55C2
0180 REP 009A 0040
0190 CHECKSUM B59B781F
0200 IDRDATA AN52494
.....+.....1.....+.....2.....+.....3.....+.....4.....+.....5...No.of.Lines: 33

```

With this screen, you can modify the DSN of the library where this correction is to be applied. In addition, you may modify the text of the correction using the standard editor commands (see Using the Editor and Help Facility).

## Display Jobs

If the function JO (Jobs) is entered as a line command in "Correction List of Library Groups", a screen with all generated correction jobs appears.

Example screen:

```

14:57:59                *** SYSTEM MAINTENANCE AID ***                1999-06-13
User:  User_ID          - Generated Correction Jobs -                  COZJBM11

Reposition to Job: _____ Environment: TEST

  Cmd      Job      Description      Status
  ---      ---      ---              ---
      Z010      SAGLIB:APPLY ZAPS      Open

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --    ++          -    +      Print      Canc

```

The following line commands may be selected and used:

- **CO.. Copy Job**  
A user who wishes to keep a job (as an example or for later usage) may enter the COPY command for this job. SMA asks for a new name and "job group". If the "Saved Jobs" function is entered from SMA's Administration Menu, the copied job can be found under the specified name.
- **DE.. Delete Job**  
With this command, a job can be deleted manually by the user. Normally, the stored generated correction jobs should be deleted by the user after successful execution of all jobs.
- **MO.. Modify Job**  
The generated correction jobs are displayed. The user can browse through the generated job, using PF7 and PF8 to scroll backwards and forwards, print the job, or modify it before submitting it to the operating system for execution. Usage of the editor for modification is explained in Using the Editor and Help Facility.  
**Note:**  
SMA is designed to make changes in the generated jobs unnecessary. If frequent changes of the jobs are required, the job skeletons which are used during JCL generation should be changed. Refer to JCL Skeletons or the appropriate report to find out which skeletons are involved.
- **PR.. Print Job**  
The selected job will be printed.
- **SU.. Submit Job**  
The generated job is passed to the operating system for execution. The status and successful execution of a job are NOT checked by SMA; this must be done by the user. Within SMA, a job can have the status:
  - OPEN: The job has been generated and has not yet been submitted.
  - SUBMITTED: The job has been submitted. It is possible to submit a job, change it and re-submit it.

## Add a Change

When the PF6 key is pressed in the "Correction List of Library Groups", the following screen is displayed:

```

16:16                      *** SYSTEM MAINTENANCE AID ***                      1999-06-09
  User: User_ID              - Add a Correction -                               COADM01

Correction number....: _____

Type of correction...: _ < Z - Zap                      >
                      < S - Source Change >
                      < L - Replace Libr. Member >

Operating system.....: OS/MVS__

Symbolic dataset name: _____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit                                     Canc

```

In this screen, a correction which is not available in a machine-readable form can be entered. The following must be specified:

- Correction number:  
Number of the change, must be unique.
- Type of correction:  
Type: Z = ZAP, S = source change, L = replace library member.
- Operating system:  
Name of the operating system.
- Symbolic dataset name:  
Symbolic name of a library as shown in the "Tapes" part of SMA.

Following this screen, the function "Modify Corrections" is invoked, allowing the user to enter the text for the new correction manually.

## Reports

When function R is entered in the Main Menu, the following screen is displayed:

---

This menu provides a number of choices for SMA's reporting facility. Two groups of SMA reports are available:

- Reports about the installation data (tapes, environments, parameters, ZAPs)
- Reports about SMA's knowledge on how to install Software AG products (Product Installation Table, usage of parameters, dependencies between products).

The different reports are also available via the REP... direct commands which are described in Printing Reports.

# Administration

When function A is entered in the Main Menu, the following screen is displayed:

---

The following administrative functions are available:

- **Global Parameters**  
Maintain parameters which do not belong to a specific environment.
- **Saved Jobs by group / by name**  
Maintain, modify, and submit jobs contained in the "saved" pool. These jobs were created with the line command Copy (CO) from generated jobs or Copy Environment Jobs (CJ) in the Environment Maintenance function.
- **SMA Profile**  
Select some general default values.
- **Tabload**  
Maintain and submit job to LOAD table data.
- **Unused Products**  
The products which are not installed in any environment are shown, and the user may select one or several of these products for deletion from SMA's internal tables. (Note that this function deletes nothing outside of SMA's tables)
- **Unused Tapes**  
When a product is deleted, the dataset information for this product is also deleted. This may result in tapes for which no dataset information is available. The user may select such tapes for deletion from SMA's internal tables.



## Global Parameters

When "Global Parameter" is selected from the "Administration" screen, the following screen is displayed:

```

There is only 1 page available.
16:21:16          *** SYSTEM MAINTENANCE AID ***          1999-06-07
User:  User_ID    - Modify Global Parameter Values -      ADPARM11

Reposition to Parameter: _____
Cmd  Name of Parameter      Value
___  MVS-LIB-ALLOC-TYPE      TRK_____
___  MVS-LIB-EXPIRATION       99365_____
___  MVS-LIB-GROUP            SAGLIB_____
___  MVS-LIB-GROUP-UNIT       3380_____
___  MVS-LIB-GROUP-VOL        SAGVOL_____
___  MVS-NAT-BATCH            NATBAT22_____
___  MVS-DSN-USER-LOAD        OPS.PROD.LOAD_____
___  MVS-DSN-ADA-LOAD         OPS.ADA5.LOAD_____
___  MVS-SVC                  247_____
___  MVS-DB-DEVICE            3380_____

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++      -      +      Print      Canc

```

The user may enter a new value or one of the line commands described below.

- **DI.. Display**  
A description of the selected parameter is displayed. (Understanding the complete set of parameters is more easily accomplished by report "P" available in SMA's "Reports" branch.) If this command is used, a screen appears.
- **LO.. Long Value**  
If the new value for a parameter does not fit into the corresponding column, the command LONG must be used. A window is displayed, allowing for the input of values with up to 72 characters. If this command is used, a pop-up window appears.

These global parameters are used whenever parameters are needed which are not fully environment dependent. In particular, this concerns:

## The "commit" skeletons / SMA-COMMIT, ZAP-COMMIT

These skeletons invoke a batch Natural nucleus which is frequently different from the one generated in the particular user environment.

The following global parameters are used in these skeletons:

- MVS-NAT-BATCH or VSE-NAT-BATCH  
Name of the batch Natural nucleus
- MVS-DSN-USER-LOAD or VSE-DSN-USER-LIB  
Name of the load library for batch
- MVS-DSN-ADA-LOAD or VSE-ADA-LIB  
Name of the Adabas load library
- MVS-SVC or VSE-SVC  
SVC number
- MVS-DB-DEVICE or VSE-DB-DEVICE  
Device type

### Note:

This list is dynamic and may grow as needed. In BS2000, this is not needed.

The following example may clarify the need for this:

The name of the batch Natural nucleus for SMA itself is not the one which is currently being installed, but it already exists, and most probably has a different name from the one currently being installed.

## Copy of datasets from tape to disk:

During execution of command LOAD or when "marking a dataset for copy" within the tape part parameters are needed for allocating and naming the dataset on disk.

The following global parameters are used for this purpose:

- MVS-LIB-GROUP or VSE-LIB-GROUP or BS2-LIB-GROUP  
High level qualifier for dataset names
- MVS-LIB-ALLOC-TYPE  
TRK, CYL or BLKS to be used in the SPACE parameter of the DD-statement
- MVS-LIB-GROUP-VOL or VSE-LIB-GROUP-VOL or BS2-LIB-GROUP-VOL  
Target disk for copying the dataset
- MVS-LIB-GROUP-UNIT or VSE-LIB-GROUP-UNIT  
Device type of this disk.

### Note:

For users of versions of SMA before SMA 1.2.1: in SMA 1.1, the global values were taken from the default environments, e.g., from environment OS/MVS or BS2000.

## Display Global Parameter

If DI (Display) is entered as a line command in "Modify Global Parameter Values" a screen appears.

Example screen:

```

10:48:11          *** SYSTEM MAINTENANCE AID ***          1999-06-08
User:  User_ID          - Display Product Parameter -          ENIPPM11

Name of parameter  EXPIRATION

Group ..... GLOBAL          Operating System #INTERN
Description .....
EXPIRATION-DATE USED IN ALL DD-CARDS FOR DATASETS FROM TAPE.


Parm value  min .          max          Format of Parm  A
Default value ... 99365
Possible values .


Change Allowed  Y

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit                                Canc

```

## Saved Jobs

When "Saved Jobs" is selected from the "Administration" screen, the following screen is displayed:

```

Commands executed.
16:28:39          *** SYSTEM MAINTENANCE AID ***          1999-06-07
User:  User_ID          - Saved Jobs -          ADSAVM11

Reposition to Job Group: _____

Cmd  Job Group          Job          Description          Status
___  AAAAAA          Report      Installation Guide      Open
___  AAADB161          I200-JKL   SETUP - JOBS          Submitted
___  AAADB161          I200-NOP   SETUP - JOBS          Submitted
___  AAADB25           I200-NOP   SETUP - JOBS          Submitted
___  AAAJBE           I060-SAT   PARM + LINK BATCH NATURAL Submitted
___  AAAJBE           I080       PARM + LINK ONLINE NATURAL Submitted
___  AAAJBE           I080-SAT   PARM + LINK ONLINE NATURAL Submitted
___  AAAJBE           I080-1     PARM + LINK ONLINE NATURAL Submitted
___  AAAJBE           I080-2     PARM + LINK ONLINE NATURAL Submitted
___  AAPFHVSE          I080       PARM + LINK ONLINE NATURAL Open
___  ABCMTH           I055       ASSEMBLIES OF BATCH NATURAL Submitted
___  AZ6A             AZ70SM5    NO DESCRIPTION AVAILABLE Submitted
___  AZ6A             I080BB     NO DESCRIPTION AVAILABLE Submitted
___  AZ6V             I052V      NO DESCRIPTION AVAILABLE Submitted

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit  --  ++      -      +      Print      Canc

```

The user may enter one of the line commands described below.

- **MO.. Modify**

The saved job is displayed. The user can browse through the jobs using PF7 and PF8 to scroll backwards and forwards, print the job, or modify it before submitting it to the operating system for execution. Usage of the editor for modification is explained in Using the Editor and Help Facility.

- **SU..Submit**

The saved job is passed to the operating system for execution. The status and successful execution of a job are **not** checked by SMA; this must be done by the user. Within SMA, a job can have the status:

- OPEN: The job has been saved and has not yet been submitted.
- SUBMITTED: The job has been submitted. It is possible to submit a job, change it and re-submit it.

- **DE.. Delete**

With this command, a job can be deleted manually by the user.

- **CO.. Copy**

The COPY command allows the user to copy saved jobs as often as is desired.

- **PR.. Print**

The selected job will be printed.

## SMA Profile

When "SMA Profile" is selected from the "Administration" screen, the following screen is displayed:

```

Modify the values you want to be changed.
13:05:24          *** SYSTEM MAINTENANCE AID ***          1999-03-10
User:  User_ID          - SMA Profile -          ADPRFM11

Printing Defaults - Page Size ..... 59
                  Printer ID ..... CMPRT 01

Language Code ..... 1 (1=English, 2=German)

Confirm SAVE ..... Y (Y,N)

Display SMA LOGO menu ..... Y (Y,N)

Changes are to be valid during this session only .. N (Y/N)

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit                               Canc

```

The following specifications can be entered or changed:

- Page size for the printouts
- Printer ID for reports and print functions
- Language code:

1 English

2 German

- Confirm SAVE in the editors and in the modify parameter screens
- Display SMA LOGO when starting

The values entered by the user are either valid for this session only (this is the default) or are stored in the SMA data file permanently if "Changes are to be valid during this session only?" is answered with "N".

## Tabload

When "Tabload" is selected from the "Administration" screen, the following window appears:

```

Enter a command, a direct command or press a PF-key.
16:30:11          *** SYSTEM MAINTENANCE AID ***          1999-06-07
User:  User_ID          - Administration -          ADMENM11

  Administration Task      Description
  -----
_ Global Paramet +-----+ and Commit
_ Saved Jobs      !
_ SMA Profile      !          SMA Table Loader          !
x Tabload          !          ! able data
_ Unused Product  !  Select area for further processing: ! any environment
_ Unused Tapes     !          ! ted products
                  !          _ Submit TABLOAD job      !
                  !          !
                  !          _ Modify TABLOAD job      !
                  !          !
                  +-----+

Command ===>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10---PF11---PF12---
      Help  Menu  Exit                                Canc

```

The following specifications can be entered or changed:

- Submit TABLOAD job to invoke the SMA Table Loader for recognition of a new tape by SMA. A window requesting submission parameters appears.
- Modify TABLOAD job for maintenance of the job text. When this function is selected, the editor screen appears.

## Unused Products

When "Unused Products" is selected from the "Administration" screen, the list of products not installed is displayed.

Example screen:

```

There is only 1 page available.
16:33:07          *** SYSTEM MAINTENANCE AID ***          19994-06-07
User:  User_ID          - Unused Products -          ADUPRM11

Reposition to Product: _____
M  Prod.  Op.Sys.  Description          Removed from Envir.
_  ADL221  OS/MVS   ADABAS BRIDGE FOR DL/I          1999-02-04 / TEST
_  ETP121  OS/MVS   ENTIRE ASYNCHRONOUS TRANSACTION SERVER 1999-01-14 / TEST
_  REV342  OS/MVS   REVIEW DATABASE          was never installed
_  XNP125  OS/MVS   XNP LIMITED LIBR. (NO INSTALL STEPS) 1999-01-07 / APPL

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  --    ++          -    +      Print          Canc

```

In the list of products displayed, the user may select the product(s) to be deleted by SMA. Candidates for deletion are the products which have been superseded by later versions from Software AG in all environments.

The following SMA table data is deleted:

- product description
- linkage of products into environment
- product datasets
- ZAPs and source changes belonging to deleted product datasets.

After marking one or several products with an "X", the user is prompted to confirm the deletion.

## Unused Tapes

When this function is selected from the "Administration" screen, the list of unused tapes is displayed.

Example screen:

```

Mark item(s) for deletion.
16:34:06          *** SYSTEM MAINTENANCE AID ***          1999-06-07
User:  User_ID          - Unused Tapes -          ADUBAM11

Reposition to Volume: _____
M   Volume  Description          Date Received
_   T18129  Test tape          1994-01-07

Command ==>
Enter-PF1---PF2---PF3---PF4---PF5---PF6---PF7---PF8---PF9---PF10--PF11--PF12---
      Help  Menu  Exit  --    ++          -    +      Print          Canc

```

In this list, the user may mark one or several tapes for deletion. Since only the tapes are shown for which all product datasets have already been deleted, the only information remaining for deletion is the tape record and the "READ ME" texts for these tapes.

After marking one or several tapes with an "X", the user is prompted to confirm the deletion.